

From EULER Project

Site: Preferences

Preferences for [access keys](#) and edit form

This page can be used as template for (personal) preferences, or set as default site preference (see below).

```
# Access keys - hold Alt (Windows IE), Shift + Alt (Firefox)
# or Control (Mac) and tap the indicated key on your keyboard
# to trigger the corresponding action.
# 'ak_view'          => 'v',          # view page
# 'ak_edit'          => 'e',          # edit page
# 'ak_history'       => 'h',          # page history
# 'ak_print'         => 'p',          # print view of page
# 'ak_recentchanges' => 'c',          # Recent Changes
# 'ak_save'          => 's',          # save page
# 'ak_saveedit'      => 'u',          # save and keep editing
# 'ak_savedraft'     => 'd',          # save as draft
# 'ak_preview'       => 'p',          # preview page
# 'ak_em'            => 'i',          # emphasized text (italic)
# 'ak_strong'        => 'b',          # strong text (bold)

# 'ak_attach'        => 'a',          # attach a file
# 'ak_backlinks'     => 'b',          # show backlinks
# 'ak_logout'        => 'l',          # log out

# Editing components
# 'e_rows'           => '20',          # rows in edit textarea
# 'e_cols'           => '70',          # columns in edit textarea
# 'Site.EditForm'    => 'Site.EditForm' # location of EditForm
```

To create personal user (browser) preferences,

- make a copy of [this page](#) somewhere, preferably as
Profiles.*insert_your_name_here*-Preferences
- edit that page with your new preferred settings,
- select [Set Preferences of this Page](#) on the page containing your newly created settings.

This sets a preference cookie on your browser which tells PmWiki where to find your personal preference settings.

To revert to the PmWiki default preferences

- select [Revert to PmWiki Default Preferences](#) to unset the preference cookie

See also [Cookbook:UserConfigurations](#) about how to customise the edit form for personal use.

Note that by default, parsing of Site.Preferences is disabled. To make it the default site preference, add

```
XLPage('prefs', "Site.Preferences");
```

to a config file (e.g. local/config.php).

Retrieved from <https://www-sop.inria.fr/mascotte/EULER/wiki/pmwiki.php/Site/Preferences>

